IRON-MAN XTR

FOLIAR APPLICATION

Cotton: 1st application of 1-4 pints per acre at 4 leaf stage, 2nd when cotton begins to square and repeat at 10-14 day intervals Field Crops: 3 applications of 1-4 pints per acre in enough water to assure good coverage. Apply at or before bloom and repeat at 10-14 day intervals.

Tree Crops: After fruit set, apply 4-8 pints per 100 gal. water. May be repeated at 10-14 day intervals.

Grain: Apply 2-4 pints per acre in 10 gallons of water to assure good coverage. 1st application at tillering. Second application 14 to 21 days after 1st application.

Turf Grass, Hay Meadows, and Bermuda grass pastures: Apply 2-4 pints per acre with enough water to assure good coverage. (Additional rates with increased volumes of water). Apply when grass begins to green and then at 20-30 day intervals.

A FOLIAR Plant Food, containing available Nitrogen, Chelated Iron, Chelated Manganese, and Chelated Zinc

GUARANTEED ANALYSIS

Available Nitrogen (N)	6.00%
Chelated Iron (Fe)	
Chelated Manganese (Mn)	
Chelated Zinc (Zn)	1.00%

Nutrients derived from Ferric Chloride, Ferrous Sulfate, Manganese Sulfate, Zinc Sulfate, and Urea. Also contains Ethylene diamine tetraacetic acid (EDTA) and other chelating agents.

-CAUTION-

Corrosive Liquid. Keep out of reach of children. Causes eye and skin irritation. May be harmful if swallowed. In case of contact, flush with water for at least 15 minutes and get medical help.



THE J.C. SMITH CO.

SAN SABA, TEXAS 76877

		- 2	
	2.5 gallon	27.5lb	12.48 kg
•	5 gallon	55lb	24.95 kg
	270 gallon	2970lb	1347.17 kg

PREPLANT SOIL APPLICATION

Broadcast: Apply 2-4 qts. per acre in enough water for even distribution.

Row Application: Apply 1-3 qts. per acre in enough water for even distribution. Apply 2 inches to the side and 2 inches below seed row.

CAUTION:

Contains Ferric Chloride. Product corrosive to stainless steel, mild steel, aluminum, brass, or any other type of metal. Suitable for use with fiberglass, polyethylene, polypropylene, or PVC. Applicator, booms, nozzles, valves, or any other part containing metal must be flushed with water after each use. Do not leave any of the product in rig overnight. Flush with water at end of the day.

CONDITIONS OF SALE

Seller warrants that the product conforms to its chemical description and is reasonably fit for the purpose stated on the label when used in accordance with directions under normal conditions of use, but neither this warranty nor any other warranty of merchantability of fitness for a particular purpose expressed or implied, extends to the use of this product contrary to label instructions or under abnormal conditions, or under conditions not reasonably foreseeable to the seller and buyer assumes the risk of any such use.